

Software Installation notes

With Profiler series are two software packages available.

ColiDrive Install procedure

ColiDrive Profiler edition

ColiDrive is the machine driving module. It is used to import different file types and process them on the machine. For more information see the ColiDrive manual.

ColiDrive install procedure

To install the ColiDrive make sure you have one COM port free and then download the software through the download page. Unzip the file and run setup.exe. Follow the instructions on screen to complete the installation.

ColiLiner Install procedure

ColiLiner Standard edition

Used as a PCB contouring software. Will read Gerber and Excellon data and convert it into contoured file so that ColiDrive can read it.

IMPORTANT: ColiLiner is a ONE SEAT LICENCE only. Please take care on which computer you want to use it, because once you request the license key and receive your activation code you will not be able to activate the software on any other computer than that one!

ColiLiner install procedure

To install the ColiLiner make sure you installed ColiDrive (see description above) and then download the software through the download page. ColiLiner.exe will extract itself to "C:\COLSETUP. Please go to this folder and run setup.exe. Follow the instructions on screen to complete the installation. Feel free to use any folder at your convenience for installation except C:\COLSETUP to install the files.

Placing ColiLiner into some other folder rather than C:\COLSETUP\ before installation may cause that the software will not install. After installation you may remove the setup folder.